

Подключение iSCSI VTL к Bareos

Подключение ленты

Установка пактов

```
yum install iscsi-initiator-utils
```

Подключение

```
iscsiadm -m discovery -t sendtargets -p 172.27.67.150 #IP адрес iscsi  
инициатора  
iscsiadm -m node -l
```

Установка пакетов

```
yum install -y bareos-storage-tape
```

/etc/bareos/bareos-sd.d/autochanger/autochanger-0.conf

```
Autochanger {  
  Name = "autochanger-0"  
  Changer Device = /dev/tape/by-id/scsi-1TANDBERGStorageLoader_AA45JC001732 #  
  adapt this, to match your storage loader  
  # an Autochanger can contain multiple drive devices  
  Device = tapedrive-0  
  Device = tapedrive-1  
  Changer Command = "/usr/lib/bareos/scripts/mtx-changer %c %o %S %a %d"  
}
```

/etc/bareos/bareos-sd.d/device/tapedrive-0.conf

```
Device { Name = "tapedrive-0" DeviceType = tape DriveIndex = 0 # default:0,  
only required if the autoloader have multiple drives. ArchiveDevice =  
/dev/tape/by-id/scsi-1HP_Ultrium_5-SCSI_C43A400001-nst MediaType = LTO  
AutoChanger = yes # default: no AutomaticMount = yes # default: no  
MaximumFileSize = 10GB # default: 1000000000 (1GB)  
}
```

/etc/bareos/bareos-sd.d/device/tapedrive-1.conf

```
Device { Name = "tapedrive-1" DeviceType = tape DriveIndex = 1 ArchiveDevice  
= /dev/tape/by-id/scsi-1HP_Ultrium_5-SCSI_C43A400002-nst MediaType = LTO  
AutoChanger = yes # default: no AutomaticMount = yes # default: no  
MaximumFileSize = 10GB # default: 1000000000 (1GB)  
}
```

/etc/bareos/bareos-dir.d/storage/Tape.conf

```
Storage { Name = Tape Address = bar-dir001 # N.B. Use a fully qualified name
here (do not use "localhost" here). Password =
"gh66GvtST3xmf0D95zWZ6VPnFGsuIrpVEQx0Yl2QiG/j" Device = autochanger-0 Media
Type = LTO Auto Changer = yes
}
```

From:

<https://micronode.ru/> - **micronode.ru**

Permanent link:

https://micronode.ru/wiki/backup/bareos/iscsi_vtlLast update: **2022/03/23 12:19**